

INSTALLATION INSTRUCTIONS

1. SYSTEM REQUIREMENTS

Before installing the program, please view the list of supported operating systems:

- ✓ Windows 8.1
- ✓ Windows Server 2012 R2
- ✓ Windows 8
- ✓ Windows Server 2012
- ✓ Windows 7 (SP1)
- ✓ Windows 7
- ✓ Windows Server 2008 R2 (SP1)
- ✓ Windows Server 2008 R2
- ✓ Windows Server 2008 (SP2)
- ✓ Windows Server 2008
- ✓ Windows Vista (SP2)
- ✓ Windows Vista (SP1)
- ✓ Windows Server 2003 R2 (SP2) with all latest updates containing WIC (Windows Imaging Component)

2. SERVER AND CLIENT

- ✓ **Server** (server computer) – main computer where SQL Server 2008 R2 will be installed and database will be stored.
- ✓ **Clients** (client computer) – computers that have access to the database.

There are two ways to install the program:


1. **Single-User**
The program will be installed only on one computer, which will be server computer.
2. **Multi-User**
The program will be installed on several computers. In this case, user should choose computer (with the best characteristics) which will be server computer. Other computers will be clients.

3. APPLICATION INSTALLATION

IMPORTANT! Unzip program files. Run Setup.exe. Preparation process of application installation will start; it may take a few minutes. Installation Wizard will be displayed. Follow the instructions in the wizard.

4. APPLICATION ACTIVATION

After installation, the program will request license. Click on the button **"Upload license"** and select the license file supplied with the program.




If you do not have license, then generate license request using the link **"Generate license request"**. Send the file as an attachment to the e-mail address: support@softmarine.org. It is necessary to activate each installed application.


5. APPLICATION SETTINGS

5.1. CONNECTION SETTING TO SQL SERVER

In some cases, client computer will not be able to connect automatically to database (SQL Server), located on server computer. Then window **"Connection setting to SQL Server"** will be automatically displayed.




In the drop-down list **"Server name"**, user must select the name of server computer or enter in this field server name or Ip-address manually. These data could be found on server computer (Settings / Connection setting to SQL Server / Information about your computer).



Click on the **"Connect"** button.

5.2. NEW DATABASE CREATION (ON SERVER COMPUTER)

If the window “**Information about databases**” is displayed on server computer, press the button “**Create new database**”.



6. AUTHORIZATION

The system can be accessed by one of the following users:

LOGIN	PASSWORD
Administrator	admin
user	user

If you want to start using complete package of the program, you need to add new users. To do this, login into the system as System Administrator (see “**User Guide**” item 2).

IMPORTANT: System Administrator does not have standard rights of ordinary registered user and has only the right to add users and edit their data.

To familiarize with the program, please login into the system as ordinary user (Login: user).



Detailed “**User Guide**” is available on the main window of the program in submenu “**Help**”.

In case of any questions, please contact us by:

e-mail: support@softmarine.org
tel. +7 812 4547511
skype: softmarine